# **AT COMMANDS**

The general syntax of AT commands for performing different functions is:

# •AT+parameter=?

When a command in this type is sent through the serial monitor, the ESP returns all the values that **parameter** can take.

# •AT+parameter=val

When a command in this type is sent through the serial monitor, the ESP sets the value of **parameter** to **val**.

# •AT+parameter?

When a command in this type is sent through the serial monitor, the ESP returns the current value of **parameter**.

Some AT commands may take only one of the above types while some may take all 3.

An example of a command that is possible in all the above 3 types is CWMODE, which is used to set the wifi mode.

## • AT

Used as a test command.

Response: **OK** should be returned.

## • AT+RST

Used to restart the module.

<u>Response</u>:ESP returns a load of garbage. However look for **Ready** or **ready**.

## • AT+GMR

Used to determine the firmware version of the module.

Response: Firmware version should be returned.

## • AT+CWMODE=?

<u>Response</u>:All the values that the ESP CWMODE can take(1-3) are returned specifically +**CWMODE(1-3)**. Where

1=Static

2=AP

3=Both static and AP

## • AT+CWMODE=1

<u>Response</u>:**OK** should be returned if there is a change in the CWMODE from it's previous value and it is set to static, else **no change** should be returned if there is no change in CWMODE value.

**IMPORTANT**:Unless CWMODE is set to 1,the commands in the later steps will not work.

## •AT+CWMODE?

<u>Response</u>: The present value of CWMODE should be returned, specically if you followed the above step +CWMODE:1 should be returned.

#### AT+CWLAP

Used to list out all the networks in the area.

<u>Response</u>: A list of all the available access points or wifi networks should be returned.

# •AT+CWJAP="SSID","password"

(including the double quotes).

Used to join a wifi network.

Response: **OK** should be returned if the module has been connected to the network.

## •AT+CWJAP?

Used to determine the network to which the ESP is currently connected.

<u>Response</u>: The network to which the ESP is connected will be returned. Specifically +**CWJAP:**"SSID"

## •AT+CWQAP

Used to disconnect from the network to which the ESP is currently connected.

Response: The ESP quits the network to which it is connected and **OK**is returned.

## •AT+CIFSR

Used to determine the IP address of the ESP.

Response: The IP address of the ESP is returned.

## • AT+CIPMODE=0

Used to set the transfer mode

Response: **OK** is returned.

0=normal mode

1=UART-WiFi passthrough mode

## •AT+CIPMUX=1

Used to set single or multiple connections

Response: **OK** is returned.

0=single connection

1=multiple connection

# • AT+CIPSTART=link ID,type,remote IP,remote port

Used to establish a TCP connection

<u>Response</u>:Linked is returned if the connection has been established.

where

**link ID**=ID of network connection (0 $\sim$ 4), used for multi-connection.

type=string, "TCP" or "UDP".

remote IP=string, remote IP address(address of the website).

**remote port**=string, remote port number( usually selected to be 80).

# •AT+CIPSEND=link ID,length

Used to send data

Response: > (greater than) is returned if the command is successful.

where

**link ID**=ID of the connection  $(0\sim4)$ , for multi-connect. Since CIPMUX has been set to 1, is 1.

**length**=data length, MAX 2048 bytes. Generally choose a large number for the length.